

RealMan Robot rm_ros_interface User Manual V1.3

RealMan Intelligent Technology (Beijing) Co., Ltd.

Revision History

No.	Date	Comment
V1.0	2024-2-18	Draft
V1.1	2024-7-8	Amend(Add teaching messages)
V1.2	2024-12-25	Amend(Add UDP reporting messages)
V1.3	2025-4-3	Amend(Adapt to API2)

目录

- 1rm_ros_interface Package Description
- 2rm_ros_interface Package Use
- 3rm_ros_interface Package Architecture Description
- 3.1 Overview of Package Files
- 4rm_ros_interface message description
- 4.1 Joint error code-Jointerrorcode_msg
- 4.2 Clearing the joint's error code-Jointerrclear_msg
- 4.3 All coordinate system names-Getallframe_msg
- 4.4 Joint motion-Movej_msg
- 4.5 Linear motion-Movel_msg
- 4.6 Circular motion-Movec_msg
- 4.7 Joint space planning to target pose-Movejp_msg
- 4.8 Joint teaching-Jointteach_msg-Jointteach_msg
- 4.9 Position teaching-Posteach_msg
- 4.10 Attitude teaching-Ortteach_msg
- 4.11 Joint transmission-Jointpos_msg
- 4.12 Pose transmission-Cartepos_msg
- 4.13 Current robotic arm state Angle and Euler angle-Armoriginalstate_msg
- 4.14 Current arm state radians and quaternion-Armstate_msg
- 4.15 Gripper's pick-Gripperpick_msg
- 4.16 Gripper's pick gripper's pick-on-Gripperpick_msg
- 4.17 Gripper reaching the given position-Gripperset_msg
- 4.18 Force-position mixing control-Setforceposition_msg
- 4.19 Six-axis force data-Sixforce_msg
- 4.20 Setting the dexterous hand posture-Handposture_msg
- 4.21 Setting the dexterous hand action sequence-Handseq_msg
- 4.22 Setting the angles of various degrees of freedom for the dexterous hand-Handangle_msg
- 4.23 Setting the dexterous hand action sequence-Handspeed_msg
- 4.24 Setting the force threshold for the dexterous hand-Handforce_msg
- 4.25 Transmissive force-position mixing control compensation-angle-Forcepositionmovejoint_msg
- 4.26 Transmissive force-position mixing control compensation-pose-Forcepositionmovejoint_msg
- 4.27 Speed open loop control-lifting mechanism-Liftspeed_msg
- 4.28 Position closed-loop control-lifting mechanism-Lift height_msg
- 4.29 Getting the state of the lifting mechanism-Liftstate_msg
- 4.30 Getting or setting UDP active reporting configuration-Setrealtimepush_msg
- 4.31 UDP manipulator status report Armcurrentstatus_msg
- 4.32 UDP joint current report Jointcurrent_msg
- 4.33 UDP joint enabling status report Jointenflag_msg
- 4.34 UDP manipulator Euler's angular pose is reported to Jointposeeuler_msg
- 4.35 UDP joint speed report Jointspeed_msg
- 4.36 UDP joint temperature report Jointtemperature_msg
- 4.37 UDP joint voltage report Jointvoltage_msg
- 4.38 System error code_Rmerr_msg
- 4.39 Basic information of the end-effector device_Rmplusbase_msg
- 4.40 Real time information of the end_effector device-Rmplusstate_msg
- 4.41 Customize high following mode joint transmission-Jointposcustom_msg
- 4.42 Customize high following mode pose transmission-Carteposcustom_msg

rm_ros_interface_Package_Description

The main function of the rm_ros_interface package is to provide necessary message files for the robotic arm to run under the framework of ROS2. In the following text, we will provide a detailed introduction to this package through the following aspects.

- 1.Package use.
- 2.Package architecture description.
- 3.Package topic description.

Through the introduction of the three parts, it can help you-

- 1.Understand the package use.
- 2.Familiar with the file structure and function of the package.
- 3.Familiar with the topic related to the package for easy development and use.

rm_ros_interface_Package_Use

This package does not have any executable commands, but it is used to provide the necessary message files for other packages.

rm_ros_interface_Package_Architecture_Description

Overview_of_Package_Files

```
— CMakeLists.txt          # compilation rule file
— include                 # dependency header file folder
  — rm_ros_interfaces
— msg                     # current message file (see below for details)
  — Armcurrentstatus.msg
  — Armoriginalstate.msg
  — Armstate.msg
  — Cartepos.msg
  — Carteposcustom.msg
  — Forcepositionmovejoint.msg
  — Forcepositionmovepose.msg
  — Force_Position_State.msg
  — Getallframe.msg
  — GetArmState_Command.msg
  — Gripperpick.msg
  — Gripperset.msg
  — Handangle.msg
  — Handforce.msg
  — Handposture.msg
  — Handseq.msg
  — Handspeed.msg
  — Handstatus.msg
  — Jointcurrent.msg
  — Jointenflag.msg
  — Jointerrclear.msg
  — Jointerrorcode.msg
  — Jointposeeuler.msg
  — Jointpos.msg
  — Jointposcustom.msg
  — Jointspeed.msg
  — Jointteach.msg
  — Jointtemperature.msg
  — Jointvoltage.msg
  — Liftheight.msg
  — Liftspeed.msg
  — Liftstate.msg
  — Movec.msg
  — Movej.msg
  — Movejp.msg
  — Movel.msg
  — Ortteach.msg
  — Posteach.msg
  — Setforceposition.msg
  — Setrealtimepush.msg
  — Sixforce.msg
```

```
└─ Stop.msg
└─ package.xml
└─ src
```

dependency declaration file

rm_ros_interface_message_description

Joint_error_code-Jointerrorcode_msg

```
uint16[] joint_error
uint8 dof
```

msg member uint16[] joint_error Error message for each joint. uint8 dof Degree of freedom message of the robotic arm.

Clearing_the_joint's_error_code-Jointerrclear_msg

```
uint8 joint_num
```

msg member joint_num the corresponding joint number, from the base to the robotic arm gripper, the number is 1-6 or 1-7.

All_coordinate_system_names-Getallframe_msg

```
string[10] frame_name
```

msg member frame_name The array of work coordinate system names returned

Joine_motion-Movej_msg

```
float32[] joint
uint8 speed
bool block
uint8 trajectory_connect
uint8 dof
```

msg member joint Joint angle, float type, unit-radians. speed Speed percentage ratio coefficient, 0-100. trajectory_connect Is the trajectory plan now. 1.wait 0.plan now. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. dof Degree of freedom message of the robotic arm.

Linear_motion-Movel_msg

```
geometry_msgs/Pose pose
uint8 speed
uint8 trajectory_connect
bool block
```

msg member pose Robotic arm pose-geometry_msgs/Pose type, x, y, z coordinates (float type, unit-m) + quaternion (float type). speed Speed percentage ratio coefficient, 0-100. trajectory_connect Is the trajectory plan now. 1.wait 0.plan now. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Circular_motion-Movec_msg

```
geometry_msgs/Pose pose_mid
geometry_msgs/Pose pose_end
uint8 speed
uint8 trajectory_connect
bool block
uint8 loop
```

msg member pose_mid Middle pose: geometry_msgs/Pose type, x, y, z coordinates (float type, unit: m) + quaternion. pose_end Target pose: geometry_msgs/Pose type, x, y, z coordinates (float type, unit: m) + quaternion. speed Speed percentage ratio coefficient, 0-100. trajectory_connect Is the trajectory plan now. 1.wait 0.plan now. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. loop Number of cycles

Joint_space_planning_to_target_pose-Movejp_msg

```
geometry_msgs/Pose pose
uint8 speed
uint8 trajectory_connect
bool block
```

msg member pose Target pose: geometry_msgs/Pose type, x, y, z coordinates (float type, unit: m) + quaternion. speed Speed percentage ratio coefficient, 0-100. trajectory_connect Is the trajectory plan now. 1.wait 0.plan now. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Joint_teaching-Jointteach_msg

```
uint8 num
uint8 direction
uint8 speed
```

msg member num joint num, 1~7. direction teach direction, 0-negative direction, 1-positive direction. speed speed:speed percentage ratio coefficient, 0-100.

Position_teaching-Posteach_msg

```
uint8 type
uint8 direction
uint8 speed
```

msg member type Teaching demonstration type: input0:X-axis direction、1:Y-axis direction、2:Z-axis direction. direction teach direction, 0-negative direction, 1-positive direction. speed speed:speed percentage ratio coefficient, 0-100.

Attitude_teaching-Ortteach_msg

```
uint8 type
uint8 direction
uint8 speed
```

msg member type Teaching demonstration type: input0:RX-axis direction、1:RY-axis direction、2:RZ-axis direction direction teach direction, 0-negative direction, 1-positive direction. speed speed:speed percentage ratio coefficient, 0-100.

Joint_transmission-Jointpos_msg

```
float32[] joint
bool follow
float32 expand
uint8 dof
```

msg member joint Joint angle, float type, unit: radians. follow Follow state, bool type, true: high follow, false: low follow, default high follow if not set. expand Expand joint, float type, unit: radians. dof Degree of freedom message of the robotic arm.

Pose_transmission-Cartepos_msg

```
geometry_msgs/Pose pose
bool follow
```

msg member pose Robotic arm poses geometry_msgs/Pose type, x, y, z coordinates (float type, unit: m) + quaternion. follow Follow state, bool type, true: high follow, false: low follow, default high follow if not set.

Current_robotic_arm_state_Angle_and_Euler_angle-Armoriginalstate_msg

```
float32[] joint
float32[6] pose
uint16 arm_err
uint16 sys_err
uint8 dof
```

msg member joint Joint angle, float type, unit: °. pose Current pose of the robotic arm, float type, x, y, z coordinates, unit: m, x, y, z Euler angle, unit: degree. arm_err Robotic arm running error code, unsigned int type. arm_err Controller error code, unsigned int type. dof Degree of freedom message of the robotic arm.

Current_arm_state_radians_and_quaternion-Armstate_msg

```
float32[] joint
geometry_msgs/Pose pose
uint16 arm_err
uint16 sys_err
uint8 dof
```

msg member joint Joint angle, float type, unit: radians. pose Current pose of the robotic arm, float type, x, y, z coordinates, unit: m, x, y, z, w quaternion. arm_err Robotic arm running error code, unsigned int type. arm_err Controller error code, unsigned int type. dof Degree of freedom message of the robotic arm.

Gripper_pick-Gripperpick_msg

```
uint16 speed
uint16 force
bool block
uint16 timeout
```

msg member speed Gripper pick speed, unsigned int type, range: 1-1000. force Gripper pick torque threshold, unsigned int type, range: 50-1000. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. timeout Set the timeout for the return, and the blocking mode will take effect (in seconds).

Gripper_pick_gripper_pick-on-Gripperpick_msg

```
uint16 speed
uint16 force
bool block
uint16 timeout
```

msg member speed Gripper pick speed, unsigned int type, range: 1-1000. force Gripper picks torque threshold, unsigned int type, range: 50-1000. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. timeout Set the timeout for the return, and the blocking mode will take effect (in seconds).

Gripper_reaching_the_given_position-Gripperset_msg

```
uint16 position
bool block
uint16 timeout
```

msg member position Gripper target position, unsigned int type, range: 1-1000, representing the degree of opening of the gripper: 0-70 mm. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. timeout Set the timeout for the return, and the blocking mode will take effect (in seconds).

Force-position_mixing_control-Setforceposition_msg

```
uint8 sensor
uint8 mode
uint8 direction
int16 n
```

msg member sensor Sensor; 0 - One-axis force; 1 - Six-axis force. mode Mode: 0 - Base coordinate system force control; 1 - Tool coordinate system force control. Direction Force control direction; 0 - Along the X-axis; 1 - Along the Y-axis; 2 - Along the Z-axis; 3 - Along the RX posture direction; 4 - Along the RY posture direction; 5 - Along the RZ posture direction. n Force value, unit: 0.1 N.

Six-axis_force_data-Sixforce_msg

```
float32 force_fx
float32 force_fy
float32 force_fz
float32 force_mx
float32 force_my
float32 force_mz
```

msg member force_fx the force along the x-axis direction. force_fy the force along the y-axis direction. force_fz the force along the z-axis direction. force_mx the force when rotating along the x-axis direction. force_my the force when rotating along the y-axis direction. force_mz the force when rotating along the z-axis direction.

Setting_the_dexterous_hand_posture-Handposture_msg

```
uint16 posture_num
bool block
uint16 timeout
```

msg member posture_num The serial number of the posture pre-saved in the dexterous hand, ranges from 1 to 40. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. timeout The timeout setting for blocking mode, unit: seconds.

Setting_the_dexterous_hand_action_sequence-Handseq_msg

```
uint16 seq_num
bool block
uint16 timeout
```

msg member seq_num The serial number of the sequence pre-saved in the dexterous hand, ranging from 1 to 40. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. timeout The timeout setting for blocking mode, unit: seconds.

Setting_the_angles_of_various_degrees_of_freedom_for_the_dexterous_hand-Handangle_msg

```
int16[6] hand_angle
bool block
```

msg member hand_angle Hand angle array, range: 0-1000. And -1 represents that no operation is performed on this degree of freedom and the current state remains. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Setting_the_dexterous_hand_action_sequence-Handspeed_msg

```
uint16 hand_speed
```

msg member hand_speed Hand speed, range: 1-1000.

Setting_the_force_threshold_for_the_dexterous_hand-Handforce_msg

```
uint16 hand_force
```

msg member hand_force Hand force, range: 1-1000.

Transmissive_force-position_mixing_control_compensation-angle-Forcepositionmovejoint_msg

```
float32[] joint
uint8 sensor
uint8 mode
int16 dir
float32 force
bool follow
uint8 dof
```

msg member joint Angle force-position mixing transmission, unit: radians. sensor Type of sensor used, 0 - One-axis force, 1 - Six-axis force. mode Mode, 0 - Along the work coordinate system, 1 - Along the tool end coordinate system. dir Force control direction, 0 to 5 represent X/Y/Z/Rx/Ry/Rz respectively, and the default direction for one-axis force type is the Z direction. force Force value, accuracy: 0.1 N or 0.1 Nm. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking. dof Degree of freedom message of the robotic arm.

Transmissive_force-position_mixing_control_compensation-pose-Forcepositionmovejoint_msg

```
geometry_msgs/Pose pose
uint8 sensor
uint8 mode
int16 dir
float32 force
bool follow
```

msg member pose Robotic arm pose message, x, y, z position message + quaternion posture message. sensor Type of sensor used, 0 - One-axis force, 1 - Six-axis force. mode Mode, 0 - Along the work coordinate system, 1 - Along the tool end coordinate system. dir Force control direction, 0 to 5 represent X/Y/Z/Rx/Ry/Rz respectively, and the default direction for one-axis force type is the Z direction. force Force value, accuracy: 0.1 N or 0.1 Nm. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Speed_open_loop_control-lifting_mechanism-Liftspeed_msg

```
int16 speed
bool block
```

msg member speed Speed percentage, -100-100. Speed 0: the lifting mechanism moves upward; Speed = 0: the lifting mechanism stops. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Position_closed-loop_control-lifting_mechanism-Lift_height_msg

```
uint16 height
uint16 speed
bool block
```

msg member height Target height, unit: mm, accuracy: 0-2600. speed Speed percentage, 1-100. block whether it is a blocking mode, bool type, true-blocking, false-non-blocking.

Getting_the_state_of_the_lifting_mechanism-Liftstate_msg

```
int16 height
int16 current
uint16 err_flag
```

msg member height Current lifting mechanism height, unit: mm, accuracy: 1mm, range: 0-2300. current Lifting drive error code, error code type refers to joint error code.

Getting_or_setting_UDP_active_reporting_configuration-Setrealtimepush_msg

```
uint16 cycle
uint16 port
uint16 force_coordinate
string ip
bool aloha_state_enable
bool arm_current_status_enable
bool expand_state_enable
bool hand_enable
bool joint_speed_enable
bool lift_state_enable
bool plus_base_enable
bool plus_state_enable
```

msg member cycle Set the broadcast cycle, which is a multiple of 5ms. port Set the port number for broadcasting. force_coordinate Coordinate system for external force data of the system, where 0 is the sensor coordinate system, 1 is the current work coordinate system, and 2 is the current tool coordinate system. ip Customized reporting target IP address. aloha_state_enable aloha master arm state enable. arm_current_status_enable arm_current_status enable. expand_state_enable Expansion joint-related data enable. hand_enable Dexterous hand state enable. joint_speed_enable Current joint speed, with an accuracy of 0.02 rpm. lift_state_enable Lifting joint data enable. plus_base_enable Basic information of the end-effector device enable. plus_state_enable Real-time information of the end-effector device enable.

UDP_manipulator_status_report-Armcurrentstatus_msg

```
uint16 arm_current_status
```

msg member arm_current_status Mechanical arm status, 0-RM_IDLE_E // Enabled but idle state 1-RM_MOVE_L_E // move L state in motion 2-RM_MOVE_J_E // move J in motion 3-RM_MOVE_C_E // move C state in motion 4-RM_MOVE_S_E // move S state in motion 5-RM_MOVE_THROUGH_JOINT_E // Angle transparent state 6-RM_MOVE_THROUGH_POSE_E // Pose transparent state 7-RM_move_through_force_pose_e//Force control transparent transmission state 8-RM_MOVE_THROUGH_CURRENT_E // Current loop transparent state 9-RM_STOP_E // Emergency stop status 10-RM_SLOW_STOP_E // slow stop status 11-RM_PAUSE_E // Pause status 12-RM_CURRENT_DRAG_E // Current loop drag status 13-RM_SENSOR_DRAG_E // Six-axis force drag state 14-RM_TECH_DEMONSTRATION_E // Teaching Status

UDP_joint_current_report-Jointcurrent_msg

```
float32[] joint_current
```

msg member joint_current Current joint current with an accuracy of 0.001mA.

UDP_joint_enabling_status_report-Jointenflag_msg

```
bool[] joint_en_flag
```

msg member joint_en_flag Current joint enabling state, 1 is up enabling and 0 is down enabling.

UDP_manipulator_Eulers angular_pose_is_reported_to-Jointposeeuler_msg

```
float32[3] euler  
float32[3] position
```

msg member euler Euler angle of current waypoint attitude, with an accuracy of 0.001rad.
position The current waypoint position has an accuracy of 0.000001M.

UDP_joint_speed_report_Jointspeed_msg

```
float32[] joint_speed
```

msg member joint_speed Current joint speed, accuracy 0.02RPM.

UDP_joint_temperature_report_Jointtemperature_msg

```
float32[] joint_temperature
```

msg member joint_temperature Current joint temperature, with an accuracy of 0.001°C.

UDP_joint_voltage_report_Jointvoltage_msg

```
float32[] joint_voltage
```

msg member joint_voltage Current joint voltage, with an accuracy of 0.001V V.

System_error_code_Rmerr_msg

```
uint8 err_len  
int32[] err
```

msg 成员 err_len uint8。 err int32。

Basic_information_of_the_end_effector_device_Rmplusbase_msg

```
string manu          # Device manufacturer;  
int8 type            # Device type, 1 - Two-finger gripper, 2 - Five-finger  
dexterous hand, 3 - Three-finger gripper;  
string hv            # Hardware version;  
string sv            # Software version;  
string bv            # Bootloader version;  
int32 id             # Device ID;  
int8 dof             # Degrees of freedom;  
int8 check           # Self-check switch;  
int8 bee             # Beeper switch;  
bool force           # Force control support;  
bool touch           # Tactile support;  
int8 touch_num       # Number of tactile sensors;  
int8 touch_sw        # Tactile switch;  
int8 hand            # Hand orientation, 1 - Left hand, 2 - Right hand;  
int32[12] pos_up     # Position upper limit
```

```

int32[12] pos_low      # Position lower limit
int32[12] angle_up     # Angle upper limit 0.01°
int32[12] angle_low    # Angle lower limit 0.01°
int32[12] speed_up     # Speed upper limit
int32[12] speed_low    # Speed lower limit
int32[12] force_up     # Force upper limit 0.001N
int32[12] force_low    # Force lower limit 0.001N

```

Real_time_information_of_the_end_effector_deviceRmplusstate_msg

```

int32 sys_state        #System status
int32[12] dof_state    #Current status of each degree of freedom (DoF)
int32[12] dof_err      #Error information of each DoF
int32[12] pos          #Current position of each DoF
int32[12] speed        #Current Speed of Each Degree of each DoF
int32[12] angle        #Current Angle of Each Degree of each DoF
int32[12] current      #Current Current of Each Degree of Freedom
int32[18] normal_force #Normal Force of Tactile Three-Dimensional Force of
Each Degree of Freedom
int32[18] tangential_force #Tangential Force of Tactile Three-Dimensional Force
of Each Degree of Freedom
int32[18] tangential_force_dir #Direction of Tangential Force of Tactile Three-
Dimensional Force of Each Degree of Freedom
uint32[12] tsa         #Tactile Self-Approach of Each Degree of Freedom
uint32[12] tma         #Tactile Mutual Approach of Each Degree of Freedom
int32[18] touch_data   #Raw Data of Tactile Sensors
int32[12] force        #Torque of Each Degree of Freedom

```

Customize_high_following_mode_joint_transmission_Jointposcustom_msg

```

float32[] joint
bool follow
float32 expand
uint8 dof
uint8 trajectory_mode
uint8 radio

```

msg member joint Joint angle, float type, unit: radians. follow Follow state, bool type, true: high follow, false: low follow, default high follow if not set. expand Expand joint, float type, unit: radians. dof Degree of freedom message of the robotic arm. trajectory_mode When the high following mode is set, multiple modes are supported, including 0- complete transparent transmission mode, 1- curve fitting mode and 2- filtering mode. radio Set the smoothing coefficient in curve fitting mode (range 0-100) or the filter parameter in filtering mode (range 0-1000). The higher the value, the better the smoothing effect.

Customize_high_following_mode_pose_transmission_Carteposcustom_msg

```

geometry_msgs/Pose pose
bool follow
uint8 trajectory_mode
uint8 radio

```

msg member pose Robotic arm poses geometry_msgs/Pose type, x, y, z coordinates (float type, unit: m) + quaternion. follow Follow state, bool type, true: high follow, false: low follow, default high follow if not set. trajectory_mode When the high following mode is set, multiple modes are supported, including 0- complete transparent transmission mode, 1- curve fitting mode and 2- filtering mode. radio Set the smoothing coefficient in curve fitting mode (range 0-100) or the filter parameter in filtering mode (range 0-1000). The higher the value, the better the smoothing effect.

It is mainly for the application of API to achieve some of the robotic arm functions; for a more complete introduction and use, please see the special document "RealMan Robotic Arm ROS2 Topic Detailed Description" ([https://github.com/kaola-zero/ros2_rm_robot/blob/main/rm_driver/doc/RealMan%20Robotic%20Arm%20rm_driver%20Topic%20Detailed%20Description%20\(ROS2\).md](https://github.com/kaola-zero/ros2_rm_robot/blob/main/rm_driver/doc/RealMan%20Robotic%20Arm%20rm_driver%20Topic%20Detailed%20Description%20(ROS2).md))."